

Import of Users

Import of Accounts from LDAP

SafeUTM implements the possibility to import accounts from the Active Directory LDAP directory (hereinafter referred to as AD). Import is carried out by LDAP/LDAPS protocols (LDAPS protocol does not require additional settings from UTM and will be used automatically if needed on the domain controller).

AD user groups can be imported into specially created SafeUTM user groups. Any name can be used for them.

In order to import users from AD, you need to perform the following actions:

1. Create a group in the SafeUTM user tree. Learn more about creating groups in the [User & Group](#) article.
2. Select this group and go to the **Active Directory** tab on the right side of the screen.
3. Select the domain to import users from (if SafeUTM is a member of several domains).
4. In **Group Type** select LDAP/AD group.
5. When you click on the **LDAP group** field, **the** Active Directory user tree will open. In the tree, select the group to import (you can also select the root group to import the entire tree).
6. When you click **Save**, user import will be carried out (it may take a few minutes).

Search

▼ All

AD

AD

> Accounting

> Developers

> Printers

> Subnet

> Wi-Fi User

+

+

+

+

+

+

+

+

+

+

GeneralActive DirectoryQuota

Domain

root.safe.local

Group type

LDAP/AD group

LDAP-filter

(objectClass=user)

LDAP-group

▼ root

Users

Computers

> System

ForeignSecurityPrincipals

> Program Data

Managed Service Accounts

Domain Controllers

Save

In the future, users will be synchronized with Active Directory automatically every 15 minutes.

If necessary, you can use the query filter. For example, if you have users and computers in the same containers, and you want to import only users, write the following text in the **LDAP filter** field:

```
( &( objectCategory=person) ( objectClass=user) )
```

It is possible to import different AD user groups to different SafeUTM groups for the convenience of assigning firewall rules, content filtering, app control, bandwidth limitation, and other modules to them.

You should not import subgroups of an already imported group, because they will automatically be imported together with the main group.

Importing Accounts from Security Groups

Active Directory users can only be imported into one SafeUTM group. Therefore, if it is in multiple Active Directory security groups, it will only appear in one of the UTM groups that were imported last.

You can import any number of AD security groups into different folders of the SafeUTM user tree.

1. Create a group in the SafeUTM user tree.
2. Select the group in the tree and go to the Active Directory tab.
3. Select the intended domain in **Domain Name**.
4. Select **AD Security Group** in **Group Type**.
5. In the field below select the intended security group from the drop-down list.
6. Click **Save**.

An example of configuring the import of users from security groups can be seen in the screenshot below:

The screenshot displays the SafeUTM user tree on the left and the configuration form on the right. The user tree shows a hierarchy starting with 'All', followed by 'AD AD' (selected), and then several subgroups: 'Accounting', 'Developers', 'Printers', 'Subnet', and 'Wi-Fi User'. Each subgroup has icons for adding, deleting, and viewing details. The configuration form on the right has three tabs: 'General', 'Active Directory' (selected), and 'Quota'. Under the 'Active Directory' tab, there are three dropdown menus: 'Domain' (set to 'root.safe.local'), 'Group type' (set to 'AD security group'), and 'Group' (set to 'Domain Admins'). A blue 'Save' button is located at the bottom of the form.

Revision #6

Created 24 August 2022 23:08:56 by Val Redman

Updated 13 October 2022 14:49:35 by Val Redman