

Quotas

In SafeUTM, it is possible to use traffic limits for users.

For each quota, you can define its validity period (hour, day, week, month, quarter). It can be assigned to users or groups in the user tree in a separate tab **Quota**. Also in this tab, you can increase and view available traffic for the current period of time and find out when the quota will be reset.

If the quota is assigned to a group, then by default it is assigned to all users of the group, as well as to nested groups. The quota inherited from the group can be changed in the priorities of the nested user or group.

If the quota is exceeded, users get into the object **Quota Exceeded**. However, by default, **no limits apply to such users**. This is why you need to create a restricting rule for the object **Quota Exceeded** in one or more SafeUTM modules (firewall, content filter, application control, speed limit).

Setting up Quota

In order to set up the quota, follow these steps:

1. Go to **Traffic Rules -> Quotas** and click on **Add**.
2. Fill in the required fields in the quota addition form:
 - **Title** – enter a custom quota name.
 - **Limit (Mb)** – set a limit of megabytes of traffic for the selected period.
 - **Limitation period** – select the validity period for which the quota will be allocated.
 - Hour - each hour
 - Day - from 12:00 am to 11:59 pm
 - Week - from 12:00 am Monday to 11:59 pm Sunday
 - Month - from 12:00 am on the 1st day of the month to 11:59 pm on the last day of the month
 - Quarter - beginning of quarters: January 1, April 1, July 1, October 1

- Check that all the data have been entered correctly and click on **Save**.

Quotas

Configure quota

Title

Limit (MB)

Limitation period

Comment

Save

Cancel

You can manage the quota using the buttons in the **Operations** column. You can enable, disable, edit and delete the quota.

Quotas

2

External traffic limits for users are measured in megabytes. If the limit is exceeded, the user enters the "Exceeded quota" object and can be limited by the access rules of the corresponding modules (firewall, bandwidth limit).

+ Add

Rows per page: 10 1-1 of 1

Title ↑	Limit (MB) for the period	Comment	Operations
Quota for Accounting	5,000 MB per month		<div><div></div><div></div><div></div></div>

Setting up User and Group

Setting up Group

The created quotas can be applied for groups of users in the tab **Quota**.

You can inherit a quota from the higher-level group, or select another quota by deactivating **Inherit quota from group** switch and selecting the required quota.

User & Group

Q Search

▼ All

➤ Accounting

➤ Developers

➤ Printers

➤ Subnet

➤ Wi-Fi User

+

+

+

+

+

+

+

+

+

+

+

+

General

Active Directory

Quota

Inherit quota from group

Quotas

Management is carried out in the Quotas section

The group **All** has a separate switch **Use quotas**. This parameter allows you to extend the use of quotas to all users.

User & Group

Q Search

▼ All

➤ Accounting

➤ Developers

➤ Printers

➤ Subnet

➤ Wi-Fi User

+

+

+

+

+

+

+

+

+

+

+

+

General

Quota

Use quotas

To save changes, select a quota

Quotas

Management is carried out in the Quotas section

Setting up Users

The created quotas can be applied to users. You can manage quotas in the **Quota** tab of the selected user.

General

Quota

IP and MAC authorization

Sessions

☐ Inherit quota from group

Quotas

Quota for Accounting

Management is carried out in the [Quotas](#) section

Quota information

Limit (MB) 5,000 MB per month

Remainder available 5,000 MB

The quota will be reset in about 1 month, 10/01/2022

Increase traffic for the current period (MB)

Increase

To restrict access to a user with an exceeded quota,
you must create appropriate rules.

In this tab, you can set up inheritance from the group to which the user belongs, or allocate a personal quota to them.

If the quota is allocated to a user, you can view the information about it, i.e. the validity period, available traffic, and the date of quota reset. Here you can also increase it by specifying the required number of megabytes and clicking on **Increase**.

! In order to delete a quota, you need to disable it for all users and groups. Otherwise, if you try to delete it, a window will appear prohibiting such action. The window can be seen in the screenshot below:

You cannot delete a quota while it is assigned to groups or users

Users

- George Johnson
- Jim Halpert

OK

Example of Setting up Actions When Quota Is Exceeded

In the example below, we will consider a case when the users having exceeded the quota (those who have fallen into Quota Exceeded object) will be denied access to all social media and video hosting services along with the speed limited to 4 Mbps. However, one user will be allowed access even in case they exceed the quota, as the employee is a marketing specialist.

1. First, you need to create a quota with a limit of 2,000 Mb per day.
2. In all groups and all users in **Quota**, the tab turns the switch to the **Inherit quota from group** to the 'enabled' position. It needs to be done only if you changed the switch position because by default all groups and users are created with the switch in the 'enabled' position.
3. Assign the created quota to the group **All** (all other groups and users will inherit the assignment of this quota).
4. Create a rule in the **content filter** to restrict access to social networks and video hosting services for users who have exceeded the quota.
5. Create a rule that allows one of the users' access to social networks even if they have exceeded the quota.
6. Create a rule that **limits the speed** for all users that is in the object **Quota Exceeded** down to 4 Mbps.

Revision #5

Created 25 August 2022 20:25:45 by Val Redman

Updated 13 October 2022 15:08:18 by Val Redman