

# Data Backup and Recovery

## Backup

Providing users with stable access to the Internet is the main task solved by the Internet gateway. However, sometimes there are situations that lead to system failures and subsequent disruption of Internet access. Depending on the complexity of the failure, it may be necessary to completely reinstall the Internet gateway and restore data from backups. In this section, you will find a description of the backup-creating process for the SafeUTM Internet gateway.

The Internet gateway supports the following types of automatic backups:

- To a network file storage via FTP
- To a network file storage via NetBIOS protocol
- To a local hard drive

To set up automatic backups, go to **Server Management -> Backup -> Settings**. A backup copy is created every day at the hour specified in the settings (it is recommended to choose the nighttime to create a backup).

You can store backups for a week or a month.

## Backup

---

Backups

**Settings**

Uploading to FTP

Uploading to CIFS

Time of daily copy creation

12:00 AM

▼

Store for:

☐ Week

☒ Month

Save

---

# Backup to Remote File Storage via FTP or to Network File Storage using NetBIOS Protocol (CIFS)

To create a setting, go to **Server Management** -> **Backup** -> **Upload to FTP server/Upload to CIFS shared folder**, check the box **Enable uploading to FTP server/to CIFS shared folder**, and fill in the appropriate fields.

The Server Address line specifies the IP address or domain of the remote FTP/NetBIOS server that will host the database copies.

The path to the directory must be specified in UNIX format.

For example, in Windows OS, the directory is opened by the following path

\\192.168.1.1\dir\_1\dir\_2\backup, so you need to enter dir\_1/dir\_2/backup in the **Directory path** field.

Using the FTP and NetBIOS(CIFS) protocols, only automatically created backups are uploaded at the frequency specified in the **Settings** tab.

---

## Backup to Local Hard Drive

It is possible to upload a backup copy from the server or from a computer to the server using the web interface or the local menu.

- **Add** button allows you to create a backup copy of the server settings. Copies of the settings are created automatically daily.
- **Apply** button allows you to restore a backup copy of the settings. It is possible to restore the settings only for the backup version like the one installed on the server.
- **Download** button allows you to download a backup copy from the server to your computer.
- **Delete** button deletes the backup from the server.

The backup management interface in the web interface is shown in the screenshot below.

## Backup



**Backups** Settings Uploading to FTP Uploading to CIFS

Used space 0.08 MB

Free space 21,471.93 MB

+ Add

Rows per page: 10 1-5 of 5 < >

<input type="checkbox"/>	Creation date	Comment	Version	Size (MB)	Operations
<input type="checkbox"/>	Sep 3, 2022, 12:00 PM	Automatic backup.	13.0 build 508	0.02	

## Managing backups via the local menu

- To create a new backup via the SafeUTM local menu, select **9** and press **Enter**. Next, enter a comment for the backup and press **Enter**.

An example of creating a backup via the local menu is shown in the screenshot below:

```
8. Enable user's firewall
9. Create new backup
10. Restore backup
11. Enable Remote Assistant
12. Technical support contacts
13. Edit server name
14. Create cluster
15. Rollback to the previous version
16. Reboot
17. Shutdown
18. Exit

Type your choice and press Enter.
# 9

Type a comment for a backup and press Enter.

Type 'c' and press Enter to cancel.
# Backup 3
Creating backup, it can take some time...
Backup created successfully.
```

- To restore the configuration from the backup, select **10** and press **Enter**. Select a backup copy from the list (if there are several copies) by entering the item of the desired copy, and pressing **Enter**. To restore from a backup, you need to reboot the server. Type **y** and then **Enter** to reboot.

An example of restoring from a backup via the local menu is shown in the screenshot below:

```
5.  
Time:      08/31/2022 12:00:36 AM  
Version:   13.0 build 508  
Comment:   Automatic backup.  
  
6.  
Time:      08/30/2022 12:00:35 AM  
Version:   13.0 build 508  
Comment:   Automatic backup.  
  
Type your choice and press Enter.  
Type 'c' and press Enter to cancel.  
# 1  
  
Backup was chosen.  
  
Time:      09/03/2022 02:30:49 PM  
Version:   13.0 build 508  
Comment:   Backup 3  
  
To restore backup you need to reboot the server.  
Would you like to reboot and restore right now?  
  
Please confirm your choice.  
  
Type 'y' and press Enter to confirmation.  
Type 'b' and press Enter to go back.  
Type 'c' and press Enter to cancel.  
#
```

When migrating UTM from one physical machine to another (disk transfer or backup restore on new hardware), the settings of all network interfaces specified before the migration will be restored. Use the trash button to remove unnecessary interfaces.

**Example:** the original version of UTM 13.X -> migrated UTM to new hardware -> configured new hardware -> upgraded -> in the Network interfaces section, old (before migration) and new (after migration and configuration) network interfaces will be displayed.

---

Revision #4

Created 27 August 2022 19:54:04 by Val Redman

Updated 13 October 2022 16:09:59 by Val Redman