

Policies

The principles of operation of the sections **Firewall**, **Application Control**, **Content Filter**, and **Traffic Shaping** with connected UTM are identical. Consider it using the **Firewall** section as an example.

Firewall

The Safe Center firewall contains only FORWARD and INPUT tables.

Any

Source

* Any

Incoming interface

Any

Destination

* Any

Outgoing interface

Any

Time of action

* Any

Action

☒ Allow

☐ Deny

Comment

Save

Cancel

An example of adding rules in Safe Center:

In Safe Center

The Forward rules created in Safe Center are displayed in two tables: **Initial** and **Final**. These tables are divided by **Local Rules on SafeUTM servers**.

An example of an empty table:

FORWARD

INPUT

The rules apply to all Safe UTM servers

+ Add

Display object names

Columns

Filters

Density

Search...

Protocol	Source	Destination	Destination ports	Action	Comment	Operations
No initial rules						
Local rules on SafeUTM servers						
No final rules						

An example of a completed table:

FORWARD

INPUT

The rules apply to all Safe UTM servers

+ Add

Display object names

Columns

Filters

Density

Search...

Protocol	Source	Destination	Destination ports	Action	Comment	Operations
* Any	IP 177.55.10.23	* Any	* Any	Deny		<div> <div></div> <div></div> <div></div> <div></div> <div></div> <div></div> </div>
Local rules on SafeUTM servers						
* Any	* Any	* Any	* Any	Allow		<div> <div></div> <div></div> <div></div> <div></div> <div></div> <div></div> </div>

Local rules on SafeUTM servers are not visible in the Safe Center interface. To view, go to the **Servers** section, click on the eye icon in the line with the required SafeUTM, and go to the **Firewall** section.

In order for the created rule to be included in the **Initial rules** table, specify the Initial value in the **Rule type** line. If you want to place the rule in the **Final rules** table, select the **Final** value.

You cannot move rules between the **Initial rules** and **Final rules** tables.

In SafeUTM

The table in SafeUTM is visually divided into three parts: top, middle, and bottom.

Operation counter

FORWARD

DNAT (port forwarding)

INPUT

SNAT

Logging

Transit traffic between interfaces

+ Add

Display object names

Columns

Filters

Density

Search...

Protocol	Source	Destination	Destination ports	Action	Comment	Operations
* Any	IP 177.55.10.23	* Any	* Any	Deny		⏻
* Any	* Any	* Any	* Any	Allow		⏻ ⛶ ⬆ ⬇ ✎ ⛶ 🗑
* Any	* Any	* Any	* Any	Allow		⏻

The rules from the connected Safe Center are transferred to the upper and lower parts. These rules cannot be managed in SafeUTM. The top part corresponds to the **Initial rules** table in the Safe Center. The lower part - the table **Final rules**.

The middle part is created by the UTM administrator in UTM itself and is not visible in the Safe Center interface.

Revision #6

Created 22 March 2023 21:11:30 by Val Redman

Updated 22 April 2023 00:47:04 by Val Redman