



# Windows 7 DNS Setup

## Step-by-step guide


1. From the Taskbar pane, **right-click** on the Wi-Fi (or LAN) icon and select **Open Network and Sharing Center**:




2. Select **Change adapter settings**.



3. **Right-click** on the current internet connection, and select **Properties**. If the system shows the security notification, click Yes.




4. We recommend disabling **Internet Protocol Version 6**. This will simplify the installation process and will have no effect on the quality of your internet connection. After that, select **Internet Protocol Version 4**, and click on **Properties**.




5. Select the option **Use the following DNS server addresses**, enter the following SafeDNS addresses:

Preferred DNS server: 195.46.39.39  
Alternate DNS server: 195.46.39.40



6. Click the **OK** button to save your settings, and **Close** the network properties window.

7. Navigate to the SafeDNS **Dashboard > Settings** and copy your IP address in the "**Enter an IP address or DynDNS**" box. Click "**Add**".



## Devices

Your IP address Copy IP address  
**[REDACTED]**

IPv4 DNS-servers addresses  
**195.46.39.39 195.46.39.40**

IPv6 DNS-servers addresses  
**2001:67c:2778::3939 2001:67c:2778::3940**

---

IP addresses/DynDNS 0/3

Add IP address or DynDNS

Enter an IP-address or DynDNS Default Select filtering policy Comment Add

Paste IP address

IP address or DynDNS x q


IP address/DynDNS	Policy	Comment
List is empty		

You have successfully configured the SafeDNS service for Windows 7.


## Troubleshooting

Please note that Windows may still be using the addresses saved in the local DNS cache. It is recommended to clean the cache by following these steps:

1. Press "**Start**"
2. Search for "**cmd**" and open the suggested application



3. Enter and run the following command in the opened window **ipconfig /flushdns**



```
C:\Windows\system32\cmd.exe
Microsoft Windows [Version 6.1.7601]
Copyright (c) 2009 Microsoft Corporation. All rights reserved.

C:\Users\SafeDNS>ipconfig /flushdns

Windows IP Configuration

Successfully flushed the DNS Resolver Cache.

C:\Users\SafeDNS>
```

[Learn more about how to clear DNS cache.](#)

Please note that settings take 5-7 minutes to apply.  
Stats and filtering status update every 10 minutes.

Revision #5

Created 28 August 2022 15:06:44

Updated 15 September 2023 21:12:34 by Val Redman